

IFSCube Manual

Daniel Ruschel Dutra

November 5, 2018

Contents

| | | |
|----------|---|-----------|
| 1 | Introduction | 5 |
| 1.1 | What is IFSCube? | 5 |
| 1.2 | Installation instructions | 5 |
| 2 | Single spectrum fitting | 7 |
| 2.1 | SPECFIT usage | 7 |
| 2.2 | Configuration file | 7 |
| 2.2.1 | fit | 7 |
| 2.2.2 | loading | 8 |
| 2.2.3 | minimization | 9 |
| 2.2.4 | continuum | 9 |
| 2.2.5 | Feature definition | 9 |
| 2.2.6 | Bounds | 10 |
| 2.2.7 | Constraints | 10 |
| 2.3 | Using SPECFIT in your own scripts | 11 |
| 3 | Datacube fitting | 13 |
| 3.1 | Configuration file | 13 |
| 3.1.1 | fit | 13 |
| 3.2 | Checking fit results | 14 |
| 3.3 | The output file | 15 |
| 4 | The IFSCube package | 17 |
| 4.1 | Basic Functions | 17 |
| 4.1.1 | Image from wavelength cut | 17 |
| 4.2 | Fitting emission lines | 18 |
| 4.2.1 | Line fitting, a basic example. | 18 |
| 4.2.2 | Setting bounds | 20 |
| 4.2.3 | Multiple lines | 21 |
| .1 | Error descriptions | 22 |

Chapter 1

Introduction

1.1 What is IFSCube?

IFSCube is a python package designed to perform analysis tasks in data cubes of integral field spectroscopy. It was originally designed to work with the data from Gemini's Multi-Object Spectrograph (GMOS), and as such, many default parameters are set to work best with this kind of data. Using it with data cubes from other instruments should be possible by explicitly setting a few more parameters.

Keep in mind that this is not a closed software that will be called from the command line and perform the tasks that you might want. Instead it is intended to be used as part of your own scripts, hopefully making them a lot more concise, and saving you a lot of time. At the same time, since everything you can do in a python script can also be done using an interactive interpreter such as ipython, you can also perform your analysis on the fly.

For the specific task of fitting spectral features there is an executable script that can be called from the command line, and controlled via an ASCII configuration file. This is the recommended method for line fitting, as many of the preparation steps can be easily set up by the configuration parser.

1.2 Installation instructions

The preferred method for the installation of IFSCube is to use pip. Pip can install directly from the git repository using the following command:

```
pip install git+https://danielrd6@bitbucket.org/danielrd6/ifscube.git
```

IFSCube uses third party programs that are not distributed with the package, namely pPXF and Voronoi Binning, written by Michelle Cappellari. If you wish to use IFSCube in conjunction with these programs you will have to install them first, by downloading and following the instructions at the following address: <http://www-astro.physics.ox.ac.uk/mxc/software/>

If you want to upgrade an existing installation of IFSCube use

```
pip install --upgrade git+https://danielrd6@bitbucket.org/danielrd6/ifscube.git
```

If you are having trouble with the Fortran compiler you can force one with pip's install options, which are exemplified below.

To force a specific compiler:

```
pip install git+https://danielrd6@bitbucket.org/danielrd6/ifscube.git
--install-option=build --install-option='--fcompiler=g95'
```

IFSCube has been extensively tested with the astroconda¹ distribution, therefore it is highly recommended that you install it within the astroconda's Python 3 environment.

If you want to be able to change the package to suit your needs, or contribute with your own code to the project, it is recommended to clone the git repository and install the package as an editable package.

```
git clone https://danielrd6@bitbucket.org/danielrd6/ifscube.git
cd ifscube
pip install -e .
```

¹<https://astroconda.readthedocs.io/en/latest/>

Chapter 2

Single spectrum fitting

One of the functions available for IFSCube allows for the fitting of a single 1D spectrum. This is very useful when experimenting parameters for the fits using a combined, higher signal-to-noise, spectrum from the data cube. There is even a executable script to perform the fits using parameters given in a configuration file.

2.1 SPECFIT usage

After the installation of IFSCube the executable SPECFIT should be available in your path. If not, the script is located in the bin directory of the IFSCube installation directory.

The simplest way to use the program is to just invoke it as

```
specfit -c halpha.cfg manga_onedspec.fits
```

Here, and in all subsequent examples, we will use the data available in the ifscube/examples directory. The above command specifies the configuration file with the **-c** option. If you want to know more about the command line options of linefit just execute it with the **-h** option, and a help page will be printed.

The configuration file halpha.cfg, present in the examples directory, showcases the syntax and some of the possibilities of SPECFIT. The reader is strongly encouraged to start with that file and modify it for her/his fits.

2.2 Configuration file

The configuration file for SPECFIT follows the formalism of typical *.ini* files, with sections defined by strings within brackets and parameter as strings followed by **:** or **=** and the corresponding value. Comments are possible, and are declared by either a **#** or a **;**. In the following subsections each section of the configuration file will be discussed in more detail. Boolean options, such as fit_continuum and overwrite take 'yes' or 'no' as values.

2.2.1 fit

This part of the configuration file sets the main options of the fitting process.

- **fit_continuum:** 'yes', 'no'
Fits a polynomial pseudo continuum before fitting the spectral features.
- **function:** 'gaussian', 'gausshermite'
Sets the function to be used as the spectral feature profile. It can be either 'gaussian' or 'gausshermite'.

- **fitting_window:** lambda_0:lambda_1
Spectral window in which to perform the fit.
- **outimage:** string
Name of the output FITS file.
- **overwrite:** 'yes', 'no'
Overwrites the output file if it already exists.
- **optimize_fit:** 'yes', 'no'
Only fits pixels that are close to the spectral features set in the configuration file. For instance, if you want to fit a spectrum that goes from 4800Å to 7000Å, but is only interested in the [O III] 5007 and [N II] 6583 lines, you can set this option to 'yes', and save the computing time required for all the zeros in between.
- **optimization_window:** number
Size of the optimized fitting window in units of the sigma given as initial guess. If optimize_fit is set to yes (see above) Only pixels with wavelength between (wavelength - optimization_window * sigma) and (wavelength + optimization_window * sigma) will be evaluated by the fitting algorithm.
- **suffix:** string
Suffix to attach to the name of the input file. The resulting concatenation will be the output file's name.
- **verbose:** 'yes', 'no'
Shows a nice progress bar.
- **writefits:** 'yes', 'no'
Writes the output of the fit to a file.
- **guess_parameters:** 'yes', 'no'
Makes an initial guess for the amplitude, centroid and sigma of each spectral feature based on the spectrum. Setting this option to yes **does not** mean that you can leave the line definition sections empty. A lot of other routines within the algorithm are based on the initial parameters you give for each spectral feature.
- **test_jacobian:** 'yes', 'no'
Checks if there are null values in the jacobian matrix of the fit. If there are, it usually means that the spectral feature is in a flagged section of the spectrum, or that the best fit is a line with zero amplitude.

2.2.2 loading

The **loading** section is dedicated to parameter that tell SPECIFY how to load your spectrum from the FITS file. Each parameter listed below takes as input value a string that should match the name of the FITS extension in the input MEF file containing the appropriate data. It is important to point out that all the extensions must match the dimensions of the observed spectrum, except for the primary, which should only contain a header.

- **scidata:** Scientific data, or the actual observed spectrum.
- **primary:** Primary extension, with the main header.
- **variance:** Pixel by pixel variance.
- **stellar:** Stellar spectrum to be subtracted from the observed spectrum before the fit.
- **flags:** Flag spectrum, with zeros setting value that should not be used.

- **redshift:** This is the only parameter that is not supposed to be a FITS extension. SPECIFY is designed to read a redshift from the primary extension header. If a 'redshift' keyword is not found, it tries to read the redshift given in the configuration file. If none is given in either way, the spectrum is assumed to be already in the rest frame.

2.2.3 minimization

This section controls the minimization algorithm, and its parameters are directly passed on to the *scipy.optimize.minimize* function. A number of different solvers are accessible via the *minimize* function, but currently SPECIFY only The reader is encouraged to read the documentation for the *scipy* function in order to gain a deeper understanding of the fitting process. In the parameter list below a few example values are offered as a suggestion.

- **eps:** (1e-2) number
Step size used for numerical approximation of the jacobian.
- **ftol:** (1e-5) number
Precision goal for the value of f in the stopping criterion.
- **disp:** 'yes', 'no'
Displays detailed information of the fit.
- **maxiter:** 100 number
Maximum number of minimization iterations.

2.2.4 continuum

This part of the configuration file sets the parameters for the fitting of the pseudo continuum. The continuum is defined as a polynomial of arbitrary degree, which is fit to the spectrum after the subtraction of the stellar component, if there is one.

Emission lines and other data points that should not be considered in the continuum fit are eliminated via an iterative rejection algorithm. For this reason, the fitting_window set in the *fit* section should provide enough room for an adequate sampling of valid continuum points.

- **degr:** integer number
Degree of the polynomial.
- **niterate:** integer number
Number of rejection iterations.
- **lower / upper_threshold:** number
The rejection threshold in units of standard deviation.

2.2.5 Feature definition

Features to be fitted are defined as sections with arbitrary names, with the exception of fit, minimization and continuum, which are reserved. The basic syntax for a feature, or spectral line, definition is as follows:

```
[feature_name]
<parameter0>: <value>, <bounds>, <constraints>
<parameter1>: <value>, <bounds>, <constraints>
...
```

The valid parameters for each feature are discussed below:

- Mandatory parameters for all fits
 - **rest_wavelength**: the rest wavelength of the spectral feature, onto which the radial velocity will be based.
 - **velocity**: radial velocity corresponding to the centroid of the spectral feature in units of km s^{-1} .
 - **sigma**: velocity dispersion corresponding to the Gaussian σ , considering $\text{FWHM} = 2\sigma\sqrt{2\log 2}$. Also in units of km s^{-1} .
 - **amplitude**: amplitude, not the integrated flux, of the spectral feature.
- Mandatory parameters for Gauss-Hermite fits
 - **h_3**: third coefficient of the Gauss-Hermite series, responsible for asymmetric deviations from a Gaussian profile.
 - **h_4**: fourth coefficient of the Gauss-Hermite series, responsible for symmetric deviations from a Gaussian profile.
- Optional parameters
 - **k_group**: stands for kinematic grouping, and it basically is an automated way to specify that the Doppler shift and sigma of all features sharing the same **k_group** should be equal. To set it, one only needs to specify an arbitrary integer number as the value for a given feature, and repeat that same number for all other features sharing the same kinematics.
 - **continuum_windows**: specifies the windows for the pseudo continuum fitting used in the equivalent width evaluation, and are not used anywhere else. It should be given as four wavelength values separated by commas.

2.2.6 Bounds

Bounds for each parameter are given in one of two ways: i) two values separated by a **:**, or ii) a single value preceded by **+-**. For instance, if you want the velocity of a given feature to be bound between plus and minus 500 km s^{-1} :

`velocity: 0, -500:500`

or

`velocity: 0, +- 500`

Bounds can also be one-sided, as in

`amplitude: 1e-15, 1e-19:`

which will be interpreted as having only the lower limit of $1e-19$ and no upper limit.

2.2.7 Constraints

Constraints are perhaps the most valuable tool for any spectral feature fitting. We already discussed the automated constraints that keep the same kinematical parameters for different spectral features using the **k_group** parameter, but SPECIFY also accepts arbitrary relations between the same parameter of different features. For instance, suppose you want fix the flux relation between two lines you know to be physically connected, such as the [N II] lines at 6548\AA and 6583\AA .

```
[n2_a]
rest_wavelength: 6548
velocity: 0
sigma: 120
amplitude: 1e-15,, n2_b / 3
k_group: 0
```

```
[n2_b]
rest_wavelength: 6583
velocity: 0
sigma: 120
amplitude: 1e-15
k_group: 0
```

The double comma before the constraint is there because value, bounds and constraints are separated by commas, and even if you do not want to set any bounds, an extra comma is necessary for the parser to correctly identify the constraint.

Now let us discuss the syntax of the constraint, which is the expression **n2_b / 3**. The parser accepts simple arithmetic operations (*, /, +, -), inequality relations (<, >), numbers and feature names. The feature name is the name given to the section containing the spectral feature parameters, and the parameters constrained are always the same parameters in different features. Currently the parser does not support relating the sigma of some line to the flux of some other line.

2.3 Using SPECFIT in your own scripts

Chapter 3

Datacube fitting

Using IFSCUBE to fit emission lines in data cubes is very similar to fitting a single spectrum, which is described in section 2. To start the fitting process you must call the CUBEFIT executable script from the command line.

```
cubefit -c halpha_cube.cfg ngc3081_cube.fits
```

Here we are using the provided example files distributed with IFSCUBE.

For more information on the available command line options of CUBEFIT, please read the help page printed by

```
cubefit -h
```

3.1 Configuration file

There are only minor differences between the configuration files of SPECIFY and CUBEFIT, which will be covered in the following subsections, each relating to a particular section of the configuration file. Please refer to section 2 for parameters and options that also apply to single spectrum fitting.

3.1.1 fit

- **individual_spec:** 'no', 'x', 'y', 'peak' or 'cofm'
If set to 'no' fits all the spectra in the datacube, else fits only one spectrum. If set to 'x', 'y' fits the spectrum in the spaxel with horizontal coordinate 'x' and vertical coordinate 'y'. 'peak' will fit only the spaxel with the highest value in an image resulting from the sum of all the pixels along the dispersion direction. 'cofm' is similar to 'peak', but uses the center of mass instead.
- **refit:** 'yes', 'no'
Uses parameters from previous successful fits as the initial guess for subsequent fits. The parameters are the average of the results for fits returning a fit_status of 0 within a given refit_radius.
- **refit_radius:** number
Radius in pixels to use when averaging parameters for the updated initial guess.
- **spiral_loop:** 'yes', 'no'
Fits the spaxels following a spiral pattern from the specified spiral_center outwards. This is particularly useful when refit is set to 'yes', since the algorithm will start from the highest signal to noise ratio spectra.

- **spiral_center:** 'x, y', 'peak' or 'cofm'

Chooses where the spiral pattern will start. See *individual_spec* above for a description of the meaning of 'x, y', 'peak' and 'cofm'.

3.2 Checking fit results

The white zone is for loading and unloading only. If you got to load or unload, go to the white zone.

Frank Zappa

The fastest way to check the results of your fit is to use the `fit_scrutinizer` program. This program has graphical user interface (GUI) that lets you select each parameter of each component, and see the image of that parameter at the same time showing the spectrum of a particular spaxel. After installation of IFSCube by the pip installer, `fit_scrutinizer` will be appended to your path, making it accessible from any directory directly from the command line.

For instance, let us take a look at that first attempt at a data cube fit, saved as `myfit.fits`. The data cube that originated it is the `ngc3081_cube.fits`, therefore the calling sequence to `fit_scrutinizer` should read

```
fit_scrutinizer ngc3081_cube.fits myfit.fits
```

This will star a GUI similar to the one in figure 3.1, but without any of the plots yet. To start plotting your results you have to select a parameter from the list at the lower left corner, and a component from the list right next to it. In this example we selected the velocity for the only component available, component “0”. Next we click “Image plot” to generate the image of the velocity for the first component in the upper left.




Figure 3.1: Example of the interface of the `fit_scrutinizer` program, showing the velocity image, and the spectrum in the spaxel (3, 5).

At this point only the image is visible, but no spectral plot will be produced until you click on either “Follow mouse” or “Plot on click”. The former will cause a new spectral plot to be generated every time the

mouse enters a new spaxel on the image at the upper left, while the latter will only plot the spectrum when you click on a spaxel.

3.3 The output file

The output file generated by CUBEFIT is a Multi-Extension FITS file (MEF), consisting of images and tables that store the results of the fitting process. This file can be accessed by any program capable of dealing with the FITS format.

Let us start by taking a look at the extensions that are present in the output file of the example fit for 'ngc3081_cube.fits'. If you have not changed the example configuration file, the output file should be named 'ngc3081_cube_linefit.fits'. I recommend opening a interactive python interpreter, such as ipython, and entering the following commands:

```
from astropy.io import fits

cube = fits.open('ngc3081_cube_linefit.fits')

cube.info()
```

The output should read:

```
Filename: ngc3081_cube_linefit.fits
No.      Name          Ver    Type          Cards  Dimensions  Format
  0  PRIMARY              1 PrimaryHDU      70      ()
  1  FITSPEC              1 ImageHDU       13      (6, 8, 1660)  float64
  2  FITCONT              1 ImageHDU       13      (6, 8, 1660)  float64
  3  STELLAR              1 ImageHDU       13      (6, 8, 1660)  float64
  4  MODEL                1 ImageHDU       13      (6, 8, 1660)  float64
  5  SOLUTION            1 ImageHDU       17      (6, 8, 10)    float64
  6  EQW_M               1 ImageHDU       17      (6, 8, 3)     float64
  7  EQW_D               1 ImageHDU       17      (6, 8, 3)     float64
  8  STATUS              1 ImageHDU       16      (6, 8)        int64
  9  MASK2D              1 ImageHDU       16      (6, 8)        int64
 10  SPECIDX             1 BinTableHDU    13      48R x 2C      ['K', 'K']
 11  PARNAMES            1 BinTableHDU    13      9R x 2C       [7A, 2A]
 12  FITCONFIG           1 BinTableHDU    13      39R x 2C      [64A, 64A])
```

There are 13 extensions within the output file, and I will now explain briefly what each of them contains.

- PRIMARY: This is just a copy of the original header extension of the input file. Ideally this should have a good description of what the science data is.
- FITSPEC: A copy of the input science data, without any changes other than a trimming to the given fitting window. It has dimensions of (columns, rows, wavelength).
- FITCONT: If a continuum was fit to the data, this extension will contain the values of that pseudo-continuum at each wavelength coordinate.
- STELLAR: The stellar continuum, or stellar population spectra, if it was supplied to CUBEFIT.

- **MODEL:** This extension contains the modeled spectrum, which is the sum of all the spectral features that were fit to the data.
- **SOLUTION:** The resulting parameters of the fit, plus the reduced χ^2 of the fit. In this case there were 3 spectral features fit with 3 parameters each, plus the χ^2 plane, resulting in a depth of 10. The exact nature of each plane is given in the PARNAMES extension.
- **EQW_M:** The equivalent width of the modelled spectral feature.
- **EQW_D:** The equivalent width measured directly on the spectrum, but with all the other spectral features subtracted.
- **STATUS:** An integer that specifies the exit status of the fit. A value of 0 signifies a successful fit.
- **MASK2D:** An image mask, applied to the datacube, specifying which spaxels were not included in the fit.
- **SPECIDX:** A table containing the spaxel coordinates of all the spaxels included in the fit.
- **PARNAMES:** A table in which the first column specifies the name of the spectral feature, and the second specifies the parameter for that spectral feature. In a gaussian fit the parameters are A, wl and s, representing the amplitude, central wavelength and sigma of the gaussian in wavelength units. For a Gauss Hermite fit the A parameter represents the integrated flux, and there is the addition of the parameters h3 and h4, which stand for the third and fourth order coefficients of the Gauss Hermite polynomial.
- **FITCONFIG:** This is a copy of the input configuration file, with the first column storing the parameter name in section.parameter notation, and the second column storing the value of that parameter.

Chapter 4

The IFSCube package

4.1 Basic Functions

The *datacube* module contains the base class *Cube*, which includes all the major methods for dealing with integral field spectroscopy data cubes, as well as some basic functions that allow a quick inspection of the data cube. Different data cubes have different ways of organizing the data, and the best way to deal with them in a programmatic manner is to write a subclass of *Cube*. The recommended usage, for a generic data cube, is always to first load your data as a *Cube* object. Modules for reading cubes processed by GIREDS¹ and PYCASSO2².

The examples in this section will use the `ngc3081_cube.fits` file, present in the examples directory.

```
from ifscube import cubetools as ct

mycube = ct.gmosdc('ngc3081_cube.fits')
```

The initialization method for *Cube* sets up a few basic variables that will be used in the analyses tasks, such as the wavelength, rest wavelength, science data, noise cube, etc. The rest wavelength specifically, is only properly set if you enter the redshift when initializing the object, such as in

```
mycube = ct.gmosdc('ngc3081_cube.fits', redshift=0.042)
```

If no redshift is given then the rest wavelength will be just a copy of the observed wavelength. In either case, all the methods within the *Cube* class will always interpret wavelengths as referring to the rest frame wavelength.

4.1.1 Image from wavelength cut

Data cubes have three dimensions, i.e. two spatial and one spectral. In order to have an image of the data cube one has to select a wavelength range, or collapse the entire cube along the spectral dimension. Often it is useful to have an image at a specific wavelength, and for that there is the *wlprojection* function. The latter takes the data cube, multiplies it by a filtering function and returns the resulting array. Two arguments are required by *wlprojection*, namely the central wavelength and the FWHM of the filtering function. Additionally, there is the optional *filtertype* argument, which selects the type of filtering used to produce the image. Currently you can choose between a box function and a gaussian.

For instance, if you want to have an image of the data cube centered on 6000 Å with a FWHM of 100 Å

```
im = a.wlprojection(6000, 100)
```

¹GIREDS is a pipeline for reducing GMOS data.

²PYCASSO2 is a package for processing data cubes, with a special focus on providing a direct way to run STARLIGHT (Cid Fernandes et al. 2001)

4.2 Fitting emission lines

One of the main purposes and motivations behind the development of IFSCube is the fitting of emission lines in the spectra of galaxies. This is a common task for 1D spectra, and therefore there is a plethora of software than can achieve it fairly well, from IRAF's *splot* onward. However, fitting data cubes requires a code that can run with little to no interaction from the user, since the modeling process is expected to run on several hundred spectra.

The *linefit* function of the *Cube* class was designed specifically for the fitting of emission or absorption lines spectroscopic data cubes. It is basically a wrapper for the *scipy.optimize.minimize* function, with the addition of many tools for doing the minimization recursively over the entire cube. The reader that wants to gain a deeper understanding of the fitting process inside *linefit* is strongly advised to read the documentation for *minimize*.

The IFSCube distribution includes a heavily spatially under sampled data cube for the NGC 3081 galaxy, which will be used in the examples below. You can find it within the *examples* directory, under the path of your installation of IFSCube.

4.2.1 Line fitting, a basic example.

The first thing you will need to do to start using the functions contained in IFSCube is to load your data cube as a *gmosdc* object. This will start the basic variables that will be used by analysis functions. IFSCube was designed to work with Multi Extension FITS files, and relies on the *astropy.io.fits* package to read them.

In a python shell, or in your script, you should start by importing the module and initializing the *gmosdc* object.

```
from ifscube import cubetools as ct
```

```
mycube = ct.gmosdc('mycube.fits')
```

In case you have a noise estimate in the form of a cube of σ , you can load it automatically by giving the extension number as a parameter to *gmosdc*. If available, this noise information will be used for plotting your spectra and for evaluating the reduced χ^2 of the line fitting.

```
mycube = ct.gmosdc('ngc3081_cube.fits', var_ext=2)
```

Now let us take a look at a particular spectrum of the data cube, using the *plotspec* method. This method takes two mandatory arguments, which are the horizontal and vertical spaxel coordinates. The following example will cause a plot of the spectrum at spaxel (3, 3) to appear.

```
mycube.plotspec(3, 3)
```

If all went well, you should see the plot in figure 4.1. The shaded smoothed region is the noise estimate from extension 2. If you do not have the noise extension this shaded region will simply not be plotted, but otherwise everything should work equally well.

If we zoom in around the $H\alpha$ region you will get a clearer picture of the emission lines, which will be instrumental in defining the initial guess for the line fitting process. Suppose now that we are only interested in fitting the [N II] line, ignoring the neighboring [N II] and $H\alpha$ lines. We should start by defining a list of initial parameters which we will call *p0*. This list has to be in the order of amplitude, central wavelength and sigma for a Gaussian profile fit.

```
p0 = [  
    1e-14, # The flux at the center of the line.  
    6635.0, # The central wavelength.  
    3.0, # The sigma in wavelength units.  
]
```




Figure 4.1: Example of the `plotspec` method.

Also, although not mandatory, it is always good to define a fitting window. This will help the code find a suitable continuum level and save time by not fitting a lot of zeros far away from the line of interest. By default, the continuum will be inferred from a polynomial fit to the spectrum with an aggressive sigma clipping. Most of the time this leads to good results, but you can change the parameters for the continuum fitting or provide a continuum entirely defined by you using the argument `copts` or setting the `mycube.cont` property. Both of these options will be discussed in more detail later. For this example we are fitting within 6500 and 6750 Å.

We should also choose a profile function for the emission line. Currently only Gaussian and Gauss-Hermite profiles are supported. We tell `linefit` which one to use by setting the argument `function='gaussian'`. For a Gauss-Hermite profile use `'gauss-hermite'`.

Finally, since we are not trying to fit the whole data cube in our first run, we should set the `individual_spec` argument to some tuple defining the coordinate of the desired spaxel, just like in the `plotspec` function discussed above.

The complete call to the `linefit` function should look like the following.

```
mycube.linefit(p0, function='gaussian', fitting_window=(6500, 6750),
               individual_spec=(3, 3))
```

When fitting a single spaxel, this function returns a lot of information that will only be stored in the `gmosdc` object during data cube runs. This behavior is particularly useful for interactive runs, as it gives immediate access to the main fit products, thus facilitating the user's evaluation of the fitting procedure.

In order to see the result of this fit, you can use the `plotfit` method, which again takes the spaxel coordinates as arguments. This method will plot every component of the fit (in this case it will be only the Gaussian profile and the continuum), the observed spectrum and the modeled spectrum.

```
mycube.plotfit(3, 3)
```

Figure 4.2 shows a zoomed in view of `plotfit`'s result. In this example the green line represents the observed spectrum, the blue line is the modeled line profile added to the continuum, and the orange line is the continuum. `Plotfit` also prints the fit parameters in the terminal, as in the example below.

A wl s
8.89e-15 6636.85 -2.05

Notice how the σ value turned out negative. Since only σ^2 is used in the Gaussian profile, the minimization algorithm can make no distinction between positive and negative values. This can be prevented by setting bounds to each parameter, which will be discussed in further detail in another section.




Figure 4.2: Example of the plotfit function.

If all went well and we are satisfied with our fitting, we can go ahead and remove the *individual_spec* argument, and let linefit run over the entire data cube. Removing this argument will cause linefit to return the fit parameters in a data cube of spatial dimensions equal to the original data, and depth equal to the number of parameters plus one. The last plane of this solution cube is the reduce χ^2 of the fit.

```
mycube.linefit(p0, function='gaussian', fitting_window=(6500, 6750))
```

Even if you do not choose to store the output in a variable, it will be stored in the mycube.em_model property. It is also advisable to save the results of the fit in a FITS file, by setting the arguments *write-fits=True* and *outimage='myfit.fits'*. This will allow you to use the *fit_scrutinizer* utility to check the results of your fits (see section 3.2).

4.2.2 Setting bounds

If perchance you went ahead and tried to fit the entire data cube with the parameters of the last section you mostly likely got disappointed with the results. Alas, life is not that simple, neither is minimization. A good fit, other than having a good initial guess, should have bounds. They prevent the minimization algorithm from wandering too far away from the physically sound parameters.

Bounds for linefit are a list of pairs, with each pair representing the minimum and maximum values of the parameters, respecting the same order of the initial guess. For instance, let us say that the amplitude should not be negative, neither should it be greater than $1e-13$. Our initial guess for the central wavelength should be within 5 Å of the correct answer and the sigma should be above 1 Å and below 6 Å. Therefore

```
b = [
    [0, 1e-13],
    [6630, 6640],
    [1, 6],
]
```

We now pass this list as an argument to `linefit` and see how that turns out.

```
mycube.linefit(p0, function='gaussian', fitting_window=(6500, 6750), bounds=b)
```

4.2.3 Multiple lines

Following the basic example of a single line fit, we will now discuss how to fit multiple lines simultaneously. The basic process remains the same, the only thing that will change is the number of parameters in the initial guess and the number of bounds. The *linefit* function is prepared to work with an arbitrarily large number of components, as long as they have the same profile function, i.e. Gaussian or Gauss-Hermite.³

In the next example we will fit both [N II] and the $H\alpha$ line. Our initial guess *p0* will be

```
p0 = [
    1e-14, # The flux at the center of the line.
    6601.0, # The central wavelength.
    3.0, # The sigma in wavelength units.

    1e-14, # The flux at the center of the line.
    6617.0, # The central wavelength.
    3.0, # The sigma in wavelength units.

    1e-14, # The flux at the center of the line.
    6635.0, # The central wavelength.
    3.0, # The sigma in wavelength units.
]
```

Of course this is a little tedious to write explicitly, and we can try to do it programmatically, like

```
lambda_0 = [6601, 6617, 6635]
p0 = []
for i in range(3):
    p0 += [1e-14, lambda_0[i], 3]
```

Or even, if you would like to have a piece of code with all the components clearly distinguished you could define three lists, one for each of the components, and later state that *p0* is the sum of all three.

```
n2a = [1e-14, 6601, 3]
ha = [1e-14, 6617, 3]
n2b = [1e-14, 6635, 3]
p0 = n2a + ha + n2b
```

The bounds can also be set programmatically based on our initial guess. For instance, if you want to keep loose bounds for the amplitude and the sigma, but want to be stringent on the central wavelength you could write

³A complementary version of *linefit* that accepts `astropy.models.FittableModel` instances instead of the internally defined functions is currently under development.

```

b = []
for i in range(0, len(p0), 3):
    b += [[0, 1e-13]] # Amplitude positive and below 1e-12
    b += [[p0[i + 1] - 5, p0[i + 1] + 5]] # Central wavelength within 5 Å
    b += [[1, 6]] # Sigma between 1Å and 6Å

```

The call to `linefit` is exactly the same as before, the only difference lies in the definition of $p0$ and b . Figure 4.3 shows the result of this fit for the spectrum in the spaxel (3, 3).




Figure 4.3: Example of a multiple component fit for the same spaxel (3, 3).

.1 Error descriptions

For each spectrum that is fitted a fit status number is returned. If the number is 0 it means that the fit was successful, otherwise something went wrong.