

# IFSCube Manual

Daniel Ruschel Dutra

February 23, 2018

## Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
1.1	What is IFSCube? . . . . .	1
1.2	Installation instructions . . . . .	2
<b>2</b>	<b>Single spectrum fitting</b>	<b>2</b>
2.1	SPECFIT usage . . . . .	2
2.2	Configuration file . . . . .	3
2.3	fit . . . . .	3
2.3.1	loading . . . . .	3
2.3.2	minimization . . . . .	4
2.3.3	continuum . . . . .	4
2.4	Feature definition . . . . .	4
2.4.1	Parameters . . . . .	5
2.4.2	Bounds . . . . .	5
2.4.3	Constraints . . . . .	5
<b>3</b>	<b>Basic Functions</b>	<b>6</b>
3.1	Image from wavelength cut . . . . .	6
<b>4</b>	<b>Fitting emission lines</b>	<b>6</b>
4.1	Line fitting, a basic example. . . . .	7
4.2	Setting bounds . . . . .	9
4.3	Multiple lines . . . . .	10
4.4	Constraints . . . . .	11
<b>5</b>	<b>Checking fit results: fit_scrutinizer</b>	<b>11</b>

## 1 Introduction

### 1.1 What is IFSCube?

IFSCube is a python package designed to perform analysis tasks in data cubes of integral field spectroscopy. It was originally designed to work with the data from Gemini’s Multi-Object Spectrograph (GMOS), and as such, many default parameters are set to work best with this kind of data. Using it with data cubes from other instruments should be possible by explicitly setting a few more parameters.

Keep in mind that this is not a closed software that will be called from the command line and perform the tasks that you might want. Instead it is intended to be used as part of your own scripts, hopefully making them a lot more concise, and saving you a lot of time. At the same time, since everything you can do in a

python script can also be done using an interactive interpreter such as ipython, you can also perform your analysis on the fly.

For the specific task of fitting spectral features there is an executable script that can be called from the command line, and controlled via an ASCII configuration file. This is the recommended method for line fitting, as many of the preparation steps can be easily set up by the configuration parser.

## 1.2 Installation instructions

The preferred method for the installation of IFSCube is to use pip. Pip can install directly from the git repository using the following command:

```
pip install git+https://danielrld6@bitbucket.org/danielrld6/ifscube.git
```

IFSCube uses third party programs that are not distributed with the package, namely pPXF and Voronoi Binning, written by Michelle Cappellari. If you wish to use IFSCube in conjunction with these programs you will have to install them first, by downloading and following the instructions at the following address: [http://www-astro.physics.ox.ac.uk/~mxc/software/ Upgrade](http://www-astro.physics.ox.ac.uk/~mxc/software/Upgrade)

If you want to upgrade an existing installation of IFSCube use

```
pip install --upgrade git+https://danielrld6@bitbucket.org/danielrld6/ifscube.git
```

If you are having trouble with the Fortran compiler you can force one with pip's install options, which are exemplified below.

To force a specific compiler:

```
pip install git+https://danielrld6@bitbucket.org/danielrld6/ifscube.git
--install-option=build --install-option='--fcompiler=g95'
```

IFSCube has been extensively tested with the astroconda<sup>1</sup> distribution, therefore it is highly recommended that you install it within the astroconda's Python 3 environment.

If you want to be able to change the package to suit your needs, or contribute with your own code to the project, it is recommended to clone the git repository and install the package as an editable package.

```
git clone https://danielrld6@bitbucket.org/danielrld6/ifscube.git
cd ifscube
pip install -e .
```

## 2 Single spectrum fitting

One of the functions available for IFSCube allows for the fitting of a single 1D spectrum. This is very useful when experimenting parameters for the fits using a combined, higher signal-to-noise, spectrum from the data cube. There is even a executable script to perform the fits using parameters given in a configuration file.

### 2.1 SPECFIT usage

After the installation of IFSCube the executable SPECFIT should be available in your path. If not, the script is located in the bin directory of the IFSCube installation directory.

The simplest way to use the program is to just invoke it as

```
specfit -c halpha.cfg ngc6300_nuc.fits
```

---

<sup>1</sup><https://astroconda.readthedocs.io/en/latest/>

Here, and in all subsequent examples, we will use the data available in the `ifscube/examples` directory. The above command specifies the configuration file with the `-c` option. If you want to know more about the command line options of `linefit` just execute it with the `-h` option, and a help page will be printed.

The configuration file `halpha.cfg`, present in the examples directory, showcases the syntax and some of the possibilities of `SPECFIT`. The reader is strongly encouraged to start with that file and modify it for her/his fits.

## 2.2 Configuration file

The configuration file for `SPECFIT` follows the formalism of typical `.ini` files, with options defined by strings within brackets and parameters as strings followed by `:` or `=` and the corresponding value. Comments are possible, and are declared by either a `#` or a `;`. In the following subsections each section of the configuration file will be discussed in more detail.

## 2.3 fit

This part of the configuration file sets the main options of the fitting process. Boolean options, such as `fit_continuum` and `overwrite` take 'yes' or 'no' as values.

- **fit\_continuum:** 'yes', 'no'  
Fits a polynomial pseudo continuum before fitting the spectral features.
- **function:** 'gaussian', 'gausshermite'  
Sets the function to be used as the spectral feature profile. It can be either 'gaussian' or 'gausshermite'.
- **fitting\_window:** `lambda_0:lambda_1`  
Spectral window in which to perform the fit.
- **outimage:** string  
Name of the output FITS file.
- **overwrite:** 'yes', 'no'  
Overwrites the output file if it already exists.
- **suffix:** string  
Suffix to attach to the name of the input file. The resulting concatenation will be the output file's name.
- **verbose:** 'yes', 'no'  
Shows a nice progress bar.
- **writefits:** 'yes', 'no'  
Writes the output of the fit to a file.

### 2.3.1 loading

The **loading** section is dedicated to parameters that tell `SPECFIT` how to load your spectrum from the FITS file. Each parameter listed below takes as input value a string that should match the name of the FITS extension in the input MEF file containing the appropriate data. It is important to point out that all the extensions must match the dimensions of the observed spectrum, except for the primary, which should only contain a header.

- **scidata:** Scientific data, or the actual observed spectrum.
- **primary:** Primary extension, with the main header.

- **variance:** Pixel by pixel variance.
- **stellar:** Stellar spectrum to be subtracted from the observed spectrum before the fit.
- **flags:** Flag spectrum, with zeros setting value that should not be used.
- **redshift:** This is the only parameter that is not supposed to be a FITS extension. SPECIFY is designed to read a redshift from the primary extension header. If a 'redshift' keyword is not found, it tries to read the redshift given in the configuration file. If none is given in either way, the spectrum is assumed to be already in the rest frame.

### 2.3.2 minimization

This section controls the minimization algorithm, and its parameters are directly passed on to the *scipy.optimize.minimize* function. A number of different solvers are accessible via the *minimize* function, but currently SPECIFY only The reader is encouraged to read the documentation for the *scipy* function in order to gain a deeper understanding of the fitting process. In the parameter list below a few example values are offered as a suggestion.

- **eps:** (1e-2) number  
Step size used for numerical approximation of the jacobian.
- **ftol:** (1e-5) number  
Precision goal for the value of f in the stopping criterion.
- **disp:** 'yes', 'no'  
Displays detailed information of the fit.
- **maxiter:** 100 number  
Maximum number of minimization iterations.

### 2.3.3 continuum

This part of the configuration file sets the parameters for the fitting of the pseudo continuum. The continuum is defined as a polynomial of arbitrary degree, which is fit to the spectrum after the subtraction of the stellar component, if there is one.

Emission lines and other data points that should not be considered in the continuum fit are eliminated via an iterative rejection algorithm. For this reason, the fitting *window* set in the *fit* section should provide enough room for an adequate sampling of valid continuum points.

- **degr:** integer number  
Degree of the polynomial.
- **niterate:** integer number  
Number of rejection iterations.
- **lower / upper\_threshold:** number  
The rejection threshold in units of standard deviation.

## 2.4 Feature definition

Features to be fitted are defined as sections with arbitrary names, with the exception of *fit*, *minimization* and *continuum*, which are reserved. The basic syntax for a feature, or spectral line, definition is as follows:

```
[feature_name]
<parameter0>: <value>, <bounds>, <constraints>
<parameter1>: <value>, <bounds>, <constraints>
...
```

### 2.4.1 Parameters

The valid parameters are for each feature are: wavelength, sigma, flux, k\_group and continuum\_windows. Wavelength, sigma and flux are mandatory for every spectral feature, and are pretty much self explanatory. Note that here **sigma is given in units of wavelength**. The last two parameters are optional, and deserve some explanation.

The parameter **k\_group** stands for kinematic grouping, and it basically is an automated way to specify that the doppler shift and sigma of all features sharing the same **k\_group** should be equal. To set it, one only needs to specify an arbitrary integer number as the value for a given feature, and repeat that same number for all other features sharing the same kinematics.

Lastly, **continuum\_windows** specifies the windows for the pseudo continuum fitting used in the equivalent width evaluation, and are not used anywhere else. It should be given as four wavelength values separated by commas.

### 2.4.2 Bounds

Bounds for each parameter are given in one of two ways: i) two values separated by a :, or ii) a single value preceded by +/- . For instance, if you want to set the wavelength for a given feature

```
wavelength: 6562.8, 6552.8:6572.8
```

or

```
wavelength: 6562.8, +-10
```

Bounds can also be one-sided, as in

```
flux: 1e-15, 1e-19:
```

which will be interpreted as having only the lower limit of 1e-19 and no upper limit.

### 2.4.3 Constraints

Constraints are perhaps the most valuable tool for any spectral feature fitting. We already discussed the automated constraints that keep the same kinematical parameters for different spectral features using the **k\_group** parameter, but SPECFIT also accepts arbitrary relations between the same parameter of different features. For instance, suppose you want fix the flux relation between two lines you know to be physically connected, such as the [N II] lines at 6548Å and 6583Å.

```
[n2_a]
wavelength: 6548
sigma: 2
flux: 1e-15,, [n2_b] / 3
k_group: 0
```

```
[n2_b]
wavelength: 6583
sigma: 2
flux: 1e-15
k_group: 0
```

The double comma before the constraint is there because value, bounds and constraints are separated by commas, and even if you do not want to set any bounds, an extra comma is necessary for the parser to correctly identify the constraint. Now let us discuss the syntax of the constraint, which is the expression

[n2.b] / 3. The parser accepts simple arithmetic operations (\*, /, +, -), numbers and feature names. The feature name is the name given to the section containing the feature parameters, and the parameters constrained are always the same parameters in different features. Currently the parser does not support relating the sigma of some line to the flux of some other line.

### 3 Basic Functions

The *cubetools* module contains all the major functions of the IFSCube package, including some basic functions that allow a quick inspection of the data cube. These functions are implemented as methods of the *gmosdc* class, so the recommended usage is always to first load your data as a *gmosdc* object. The examples in this section will use the `ngc3081_cube.fits` file, present in the `examples` directory.

```
from ifscube import cubetools as ct

mycube = ct.gmosdc('ngc3081_cube.fits')
```

The initialization method for *gmosdc* sets up a few basic variables that will be used in the analyses tasks, such as the wavelength, rest wavelength, science data, noise cube, etc. The rest wavelength specifically, is only properly set if you enter the redshift when initializing the object, such as in

```
mycube = ct.gmosdc('ngc3081_cube.fits', redshift=0.042)
```

If no redshift is given then the rest wavelength will be just a copy of the observed wavelength. In either case, all the methods within the *gmosdc* class will always interpret wavelengths as referring to the rest frame wavelength.

#### 3.1 Image from wavelength cut

Data cubes have three dimensions, i.e. two spatial and one spectral. In order to have an image of the data cube one has to select a wavelength range, or collapse the entire cube along the spectral dimension. Often it is useful to have an image at a specific wavelength, and for that there is the *wlprojection* function. The latter takes the data cube, multiplies it by a filtering function and returns the resulting array. Two arguments are required by *wlprojection*, namely the central wavelength and the FWHM of the filtering function. Additionally, there is the optional *filtertype* argument, which selects the type of filtering used to produce the image. Currently you can choose between a box function and a gaussian.

For instance, if you want to have an image of the data cube centred on 6000 Å with a FWHM of 100 Å

```
im = a.wlprojection(6000, 100)
```

### 4 Fitting emission lines

One of the main purposes and motivations behind the development of IFSCube is the fitting of emission lines in the spectra of galaxies. This is a common task for 1D spectra, and therefore there is a plethora of software than can achieve it fairly well, from IRAF's *splot* onward. However, fitting data cubes requires a code that can run with little to no interaction from the user, since the modeling process is expected to run on several hundred spectra.

The *linefit* function of the *gmosdc* class was designed specifically for the fitting emission features in spectroscopic data cubes. It is basically a wrapper for the *scipy.optimize.minimize* function, with the addition of many tools for doing the minimization recursively over the entire cube. The reader that wants to gain a deeper understanding of the fitting process inside *linefit* is strongly advised to read the documentation for *minimize*.

The IFSCube distribution includes a heavily spatially under sampled data cube for the NGC 3081 galaxy, which will be used in the examples below. You can find it within the *examples* directory, under the path of your installation of IFSCube. All the examples in this manual will refer to this data cube.

## 4.1 Line fitting, a basic example.

The first thing you will need to do to start using the functions contained in IFSCube is to load your data cube as a *gmosdc* object. This will start the basic variables that will be used by analysis functions. IFSCube was designed to work with Multi Extension FITS files, and relies on the *astropy.io.fits* package to read them.

In a python shell, or in your script, you should start by importing the module and initializing the *gmosdc* object.

```
from ifscube import cubetools as ct
```

```
mycube = ct.gmosdc('mycube.fits')
```

In case you have a noise estimate in the form of a cube of  $\sigma$ , you can load it automatically by giving the extension number as a parameter to *gmosdc*. If available, this noise information will be used for plotting your spectra and for evaluating the reduced  $\chi^2$  of the line fitting.

```
mycube = ct.gmosdc('ngc3081_cube.fits', var_ext=2)
```

Now let us take a look at a particular spectrum of the data cube, using the *plotspec* method. This method takes two mandatory arguments, which are the horizontal and vertical spaxel coordinates. The following example will cause a plot of the spectrum at spaxel (3, 3) to appear.

```
mycube.plotspec(3, 3)
```

If all went well, you should see the plot in figure 1. The shaded smoothed region is the noise estimate from extension 2. If you do not have the noise extension this shaded region will simply not be plotted, but otherwise everything should work equally well.

If we zoom in around the  $H\alpha$  region you will get a clearer picture of the emission lines, which will be instrumental in defining the initial guess for the line fitting process. Suppose now that we are only interested in fitting the [N II] line, ignoring the neighboring [N II] and  $H\alpha$  lines. We should start by defining a list of initial parameters which we will call *p0*. This list has to be in the order of amplitude, central wavelength and sigma for a Gaussian profile fit.

```
p0 = [
    1e-14, # The flux at the center of the line.
    6635.0, # The central wavelength.
    3.0, # The sigma in wavelength units.
]
```

Also, although not mandatory, it is always good to define a fitting window. This will help the code find a suitable continuum level and save time by not fitting a lot of zeros far away from the line of interest. By default, the continuum will be inferred from a polynomial fit to the spectrum with an aggressive sigma clipping. Most of the time this leads to good results, but you can change the parameters for the continuum fitting or provide a continuum entirely defined by you using the argument *copts* or setting the *mycube.cont* property. Both of these options will be discussed in more detail later. For this example we are fitting within 6500 and 6750 Å.

We should also choose a profile function for the emission line. Currently only Gaussian and Gauss-Hermite profiles are supported. We tell linefit which one to use by setting the argument *function='gaussian'*. For a Gauss-Hermite profile use 'gauss-hermite'.




Figure 1: Example of the plotspec method.

Finally, since we are not trying to fit the whole data cube in our first run, we should set the *individual\_spec* argument to some tuple defining the coordinate of the desired spaxel, just like in the *plotspec* function discussed above.

The complete call to the linefit function should look like the following.

```
mycube.linefit(p0, function='gaussian', fitting_window=(6500, 6750),
               individual_spec=(3, 3))
```

When fitting a single spaxel, this function returns a lot of information that will only be stored in the *gmosdc* object during data cube runs. This behavior is particularly useful for interactive runs, as it gives immediate access to the main fit products, thus facilitating the user's evaluation of the fitting procedure.

In order to see the result of this fit, you can use the *plotfit* method, which again takes the spaxel coordinates as arguments. This method will plot every component of the fit (in this case it will be only the Gaussian profile and the continuum), the observed spectrum and the modeled spectrum.

```
mycube.plotfit(3, 3)
```

Figure 2 shows a zoomed in view of *plotfit*'s result. In this example the green line represents the observed spectrum, the blue line is the modeled line profile added to the continuum, and the orange line is the continuum. *Plotfit* also prints the fit parameters in the terminal, as in the example below.

```
A          wl          s
8.89e-15    6636.85     -2.05
```

Notice how the  $\sigma$  value turned out negative. Since only  $\sigma^2$  is used in the Gaussian profile, the minimization algorithm can make no distinction between positive and negative values. This can be prevented by setting bounds to each parameter, which will be discussed in further detail in another section.

If all went well and we are satisfied with our fitting, we can go ahead and remove the *individual\_spec* argument, and let *linefit* run over the entire data cube. Removing this argument will cause *linefit* to return






Figure 2: Example of the plotfit function.

the fit parameters in a data cube of spatial dimensions equal to the original data, and depth equal to the number of parameters plus one. The last plane of this solution cube is the reduce  $\chi^2$  of the fit.

```
mycube.linefit(p0, function='gaussian', fitting_window=(6500, 6750))
```

Even if you do not choose to store the output in a variable, it will be stored in the `mycube.em_model` property. It is also advisable to save the results of the fit in a FITS file, by setting the arguments `writefits=True` and `outimage='myfit.fits'`. This will allow you to use the `fit_scrutinizer` utility to check the results of your fits (see section 5).

## 4.2 Setting bounds

If perchance you went ahead and tried to fit the entire data cube with the parameters of the last section you mostly likely got disappointed with the results. Alas, life is not that simple, neither is minimization. A good fit, other than having a good initial guess, should have bounds. They prevent the minimization algorithm from wandering too far away from the physically sound parameters.

Bounds for linefit are a list of pairs, with each pair representing the minimum and maximum values of the parameters, respecting the same order of the initial guess. For instance, let us say that the amplitude should not be negative, neither should it be greater than  $1e-13$ . Our initial guess for the central wavelength should be within 5 Å of the correct answer and the sigma should be above 1 Å and below 6 Å. Therefore

```
b = [
    [0, 1e-13],
    [6630, 6640],
    [1, 6],
]
```

We now pass this list as an argument to linefit and see how that turns out.

```
mycube.linefit(p0, function='gaussian', fitting_window=(6500, 6750), bounds=b)
```

### 4.3 Multiple lines

Following the basic example of a single line fit, we will now discuss how to fit multiple lines simultaneously. The basic process remains the same, the only thing that will change is the number of parameters in the initial guess and the number of bounds. The *linefit* function is prepared to work with an arbitrarily large number of components, as long as they have the same profile function, i.e. Gaussian or Gauss-Hermite.<sup>2</sup>

In the next example we will fit both [N II] and the H $\alpha$  line. Our initial guess *p0* will be

```
p0 = [  
    1e-14, # The flux at the center of the line.  
    6601.0, # The central wavelength.  
    3.0, # The sigma in wavelength units.  
  
    1e-14, # The flux at the center of the line.  
    6617.0, # The central wavelength.  
    3.0, # The sigma in wavelength units.  
  
    1e-14, # The flux at the center of the line.  
    6635.0, # The central wavelength.  
    3.0, # The sigma in wavelength units.  
]
```

Of course this is a little tedious to write explicitly, and we can try to do it programatically, like

```
lambda_0 = [6601, 6617, 6635]  
p0 = []  
for i in range(3):  
    p0 += [1e-14, lambda_0[i], 3]
```

Or even, if you would like to have a piece of code with all the components clearly distinguished you could define three lists, one for each of the components, and later state that *p0* is the sum of all three.

```
n2a = [1e-14, 6601, 3]  
ha = [1e-14, 6617, 3]  
n2b = [1e-14, 6635, 3]  
p0 = n2a + ha + n2b
```

The bounds can also be set programatically based on our initial guess. For instance, if you want to keep loose bounds for the amplitude and the sigma, but want to be stringent on the central wavelength you could write

```
b = []  
for i in range(0, len(p0), 3):  
    b += [[0, 1e-13]] # Amplitude positive and below 1e-12  
    b += [[p0[i + 1] - 5, p0[i + 1] + 5]] # Central wavelength within 5 Å  
    b += [[1, 6]] # Sigma between 1Å and 6Å
```

The call to *linefit* is exactly the same as before, the only difference lies in the definition of *p0* and *b*. Figure 3 shows the result of this fit for the spectrum in the spaxel (3, 3).

---

<sup>2</sup>A complementary version of *linefit* that accepts *astropy.models.FittableModel* instances instead of the internally defined functions is currently under development.




Figure 3: Example of a multiple component fit for the same spaxel (3, 3).

#### 4.4 Constraints

The next important topic on a good fit is constraints. Constraints allow you to define relations between parameters, which is a

### 5 Checking fit results: `fit_scrutinizer`

*The white zone is for loading and unloading only. If you got to load or unload, go to the white zone.*

Frank Zappa

The fastest way to check the results of your fit is to use the `fit_scrutinizer` program. This program has graphical user interface (GUI) that lets you select each parameter of each component, and see the image of that parameter at the same time showing the spectrum of a particular spaxel. After installation of IFSCube by the pip installer, `fit_scrutinizer` will be appended to your path, making it accessible from any directory directly from the command line.

For instance, let us take a look at that first attempt at a data cube fit, saved as `myfit.fits`. The data cube that originated it is the `ngc3081_cube.fits`, therefore the calling sequence to `fit_scrutinizer` should read

```
fit_scrutinizer ngc3081_cube.fits myfit.fits
```

This will start a GUI similar to the one in figure 4, but without any of the plots yet. To start plotting your results you have to select a parameter from the list at the lower left corner, and a component from the list right next to it. In this example we selected the velocity for the only component available, component “0”. Next we click “Image plot” to generate the image of the velocity for the first component in the upper left.

At this point only the image is visible, but no spectral plot will be produced until you click on either “Follow mouse” or “Plot on click”. The former will cause a new spectral plot to be generated every time the mouse enters a new spaxel on the image at the upper left, while the latter will only plot the spectrum when you click on a spaxel.




Figure 4: Example of the interface of the fit\_scrutinizer program, showing the velocity image, and the spectrum in the spaxel (3, 5).